



Operation Guide



Overall operation

- Click: Click Parameter black area for focus
- ↑ ↓: Move focus parameter
- SHIFT + ↑ ↓: Move block unit
- SHIFT + ← →: Parameter set for "inc unit"
- r: set default parameter
- SHIFT + r: set default parameters for block unit
- SPACE: Start/Stop for wave sampling

Parameter manipulation (Blue : selection)

- wheel: change of selection
- ← →: change of selection
- click: change of selection
- SHIFT: change of selection (inverse order)

Parameter manipulation (Green : for number)

- wheel: change of number
- SHIFT + wheel: change of number (large)
- ← →: change of number ("inc unit")
- 0~9 . + -: direct input for number

Mouse operation in the waveform display area

- Information display of mouse cursor position
- Display information on the area created by dragging